


MAC address lookup for Windows XP

1. To find your MAC address go to Start → Run → and type cmd. Then click ok.



2. At command prompt type, ipconfig /all

3. For your wireless Mac Address look at list and find Ethernet adapter wireless connection. The Mac address will be a series of numbers and letters separated by dashes.

```
C:\WINDOWS\system32\cmd.exe
Microsoft Windows XP [Version 5.1.2600]
(C) Copyright 1985-2001 Microsoft Corp.

C:\Documents and Settings\User>ipconfig /all

Windows IP Configuration

Host Name . . . . . : UNIVERSI-BAD776
Primary Dns Suffix . . . . . :
Node Type . . . . . : Hybrid
IP Routing Enabled. . . . . : No
WINS Proxy Enabled. . . . . : No
DNS Suffix Search List. . . . . : eagleair.usm.edu

Ethernet adapter Wireless Network Connection:

Connection-specific DNS Suffix . : eagleair.usm.edu
Description . . . . . : 11a/b/g Wireless LAN Mini PCI Adapter #11
Physical Address. . . . . : 00-14-A4-11-54-8A
Dhcp Enabled. . . . . : Yes
Autoconfiguration Enabled . . . . . : Yes
IP Address. . . . . : 131.95.174.47
Subnet Mask . . . . . : 255.255.240.0
Default Gateway . . . . . : 131.95.160.1
DHCP Server . . . . . : 11.1.1.1
DNS Servers . . . . . : 131.95.84.2
                        198.49.215.21
Primary WINS Server . . . . . : 131.95.82.169
Secondary WINS Server . . . . . : 131.95.82.7
Lease Obtained. . . . . : Wednesday, August 22, 2007 3:30:44 P
Lease Expires . . . . . : Wednesday, August 22, 2007 5:30:44 P

Ethernet adapter Local Area Connection:

Media State . . . . . : Media disconnected
Description . . . . . : Broadcom NetXtreme Gigabit Ethernet
Physical Address. . . . . : 00-11-25-AD-04-12

C:\Documents and Settings\User>
```